


Quick Installation Guide for epiDOCX R5.6 Software

The Installation of epiDOCX Software is quick, simple and easy.

The minimum and recommended system requirements for installing and running epiDOCX software on a Microsoft windows based system are listed below.

Hardware Requirements	Minimum	Recommended
Processor	700 MHz processor	1 GHz
Memory	512 MB	1 GB
Free Disk Space for Installation	Space required for the installation program: 100 MB Space required for the actual installation : 60-80 MB depending on the system files already present on your computer	100MB
Video adapter and Monitor	SVGA (800 X 600) , 16-bit-color	SVGA (1024 X 768), 32-bit-color
Software Requirements	Minimum	Recommended
Supported Operating Systems	Microsoft Windows 2000 Professional (with SP4) Microsoft Windows XP Professional (with SP2) Microsoft Windows Vista (32-bit Business and Ultimate Editions)	Microsoft Windows XP Professional (with SP2)
Privileges	While installing epiDOCX, you must be logged on to your Windows system as an administrator or a member of administrator group	
Browser	Microsoft Internet Explorer 6.0	Microsoft Internet Explorer 6.0 or 7.0
Adobe Reader (For viewing PDF documents)	Adobe Reader 6.0	


 Note	The minimum system requirements must be met for epiDOCX software to install and run on your system, and the recommended system requirements, if met, will offer better and optimal software performance.
--	--

Installing epiDOCX R5.6 Software


The Installation procedure of epiDOCX Software is simple and easy. The on-screen wizard will take you through the installation process. Please make sure that the minimum system requirements are met satisfactorily before proceeding with the installation.

Installing epiDOCX Software on Microsoft windows based system from the Installation media:

1. Log on to the system on which to install epiDOCX as an administrator or a member of administrator group.
2. To begin installation, double-click **setup.exe** directly from the installation media. The setup program starts automatically and launches the epiDOCX setup initialization wizard.

 Note	Installation may abort at this point if the user's computer system does not meet the minimum system requirements.
--	---

3. The Welcome screen of the epiDOCX Setup wizard is displayed which will guide you through the rest of the installation.

 Note	The system may prompt for a restart at the end of the installation. If so, please restart the system and log on as a member of administrator group.
--	---

Third-Party products installed by epiDOCX:

Third-Party Product	Version	Comments
Image Optimizer ActiveX Control (ImageOptimizer.ocx)	3.0	Installed by epiDOCX setup and is used by the epiDOCX Editor. This is used for the compression of images while publishing documents.
DHTML Editing Control for applications (DhtmlEd.msi)	1.0	Installed by epiDOCX setup (Only on Windows Vista) and is used to enable compatibility for MS Access 2003, and other applications which previously relied on this control in Windows XP and Windows 2003.
Techsmith program (tscc.exe)	2.0	This is used for the compression of images while packing epiDOCX tasks.
Codejock.SkinFramework.v10.4.1.ocx	11.2.0	This is used for implementing skins for epiDOCX UI
Codejock.Controls.v11.2.0.ocx	11.2.0	This is used For using graphical good looking controls
PDF995.exe	1.103	Installed by epiDOCX setup and is used by epiDOCX Editor for publishing PDF documents.
Vsflex7N.ocx	7.0.0.78	Installed by epiDOCX setup and is used by Task reviewer and epiDOCX Editor for displaying the grid.

Activating epiDOCX R5.6 Software

Before you start using the product, you must activate the epiDOCX Software.

A few important points which should be kept in mind before proceeding with the Activation of the epiDOCX Software are as follows:

1. You must have successfully installed the epiDOCX Software on your Windows based system.
2. You must have the activation unlock key code with you before the activation.

Uninstalling epiDOCX R5.6 Software

Uninstalling epiDOCX Software from a Microsoft Windows based system:

The Uninstallation procedure of epiDOCX Software is also quite simple and easy.

1. Log on to the system on which to uninstall epiDOCX as an administrator or a member of administrator group.
2. Uninstall epiDOCX from your computer system using the Add or Remove Programs via control panel to remove all the components from your computer.



Note

- If your computer is connected to a network, network policy settings may also prevent you from uninstalling epiDOCX.
- The system may prompt for a restart at the end of the Uninstallation. If so, please restart the system immediately or else the future installations of the product may not work.

If you have any questions about installing or using this Software, please contact epidocxsupport@epiance.com.